

ScreenPrint Pro — User Guide

Version: 2.0
Last Updated: February 2026
Audience: Designers and pre-press operators working with textile screen printing color separation.


Table of Contents

- 1. [System Overview](#)
- 2. [Quick Start Workflow](#)
- 3. [Image Upload & Output Size](#)
- 4. [Ink Palette Management](#)
- 5. [Separation Engines](#)
 - [5.1 Vector \(Solid\)](#)
 - [5.2 Raster \(Soft / Gradient\)](#)
- 6. [Understanding the Gradient System \(Raster\)](#)
 - [6.1 How Color Distance Works](#)
 - [6.2 The Gradient Formula](#)
 - [6.3 Per-Channel Gradient Overrides](#)
 - [6.4 Practical Scenario: Gradient Between Only 2 of 5 Colors](#)
- 7. [Color Distance Methods](#)
- 8. [Pre-Processing \(Denoise\)](#)
- 9. [Cleanup & Refinement](#)
- 10. [Substrate Knockout](#)
- 11. [Halftone \(Bitmap\)](#)
- 12. [AI Auto-Config](#)
- 13. [Train IA \(Machine Learning\)](#)
- 14. [Export Options](#)
- 15. [Loadouts \(Presets\)](#)
- 16. [Layer Operations \(Pro-Shop\)](#)
- 17. [Keyboard Shortcuts & Tips](#)
- 18. [Parameter Reference Table](#)
- 19. [Glossary](#)

1. System Overview

ScreenPrint Pro is a browser-based color separation tool built specifically for **textile screen printing (serigraphy)**. It runs entirely in your browser using a **Python scientific computing engine** (Pyodide) for professional-grade image processing.

How It Works (High Level)



Export (ZIP/
Composite/PSD)

Technology Stack

Component	Technology	Purpose
Color Science	scikit-image (CIEDE2000)	Perceptually accurate color distance
Image Processing	OpenCV + NumPy	Fast pixel manipulation and morphology
Palette Detection	K-Means (CIELAB space)	Automatic ink color extraction
Halftoning	Custom AM / PIL Floyd-Steinberg	Print-ready dot patterns
AI Analysis	Google Gemini 2.5 Flash	Automatic configuration suggestions

2. Quick Start Workflow

- Upload** your design image (PNG, JPG, or PDF)
- Set **Max Colors** (e.g., 6) and click **Auto** to detect dominant colors
- Choose your **Separation Engine**: Vector (solid) or Raster (gradient)
- Click **Run Separation** to generate color channels
- Optionally click **Apply Bitmaps** to convert to halftone dots
- Export** as ZIP (individual channels) or composite preview

3. Image Upload & Output Size

Upload Zone

Accepts PNG, JPG, and PDF files. PDFs are converted to raster using PDF.js. Drag & drop or click to browse.

Output Size Panel

Controls the final resolution of the processed image. **This is critical for print quality.**

Parameter	Range	Default	Description
DPI	72–600	300	Dots Per Inch. Use 300 for standard screen printing. Higher values increase processing time significantly.
Size (inches)	1–30	3	The physical size of the output in inches.
Measurement	Width / Height	Width	Whether the size value refers to width or height of the output. The other dimension is calculated proportionally.

[!TIP] A 13" × 17" design at 300 DPI = 3900 × 5100 pixels. This is very large and will take 30+ seconds to process. For previewing, use a smaller size (3–5 inches) and only increase for the final export.

4. Ink Palette Management

The palette defines **which ink colors** will be used for separation. Each color in the palette becomes one separation channel (one screen in printing).

Auto Detection

- Set the **Max** dropdown to the desired number of colors (2–12)
- Click **Auto** to run **K-Means clustering** in **CIELAB** color space
- The algorithm samples pixels from the image and groups them into the specified number of clusters
- The `sampleSize` parameter (default: 25,000) controls how many pixels are sampled

Manual Ink Addition

- Use the color picker or type a hex code (e.g., `#FF0000`)
- Click **+** to add the color to the palette
- Manual colors are automatically **locked** (won't be overwritten by Auto)

Color Editing

- Click on any hex code in the palette to edit it directly
- Colors can be removed with the trash icon

Per-Channel Gradient Controls (Raster Mode Only)

When in **Raster** mode, each color shows a slider icon (⌵). Clicking it reveals three controls per color:

Control	Range	Default	Description
Solidez (Min)	0–100	Auto (0)	The color distance below which ink is 100% solid . Higher values = larger solid core.
Alcance (Max)	5–200	Auto (60)	The color distance at which ink fades to 0% . Higher values = wider gradient reach.
Gamma	0.1–3.0	Auto (1.25)	Curve adjustment for the gradient falloff. Values < 1 = more ink in transitions. Values > 1 = less ink, sharper cutoff.

*[!IMPORTANT] These per-channel overrides are the **most powerful tool** for controlling gradients. See [Section 6](#) for a full explanation.*

5. Separation Engines

5.1 Vector (Solid)

What it does: Assigns each pixel to exactly ONE color — the closest match in the palette. The result is a flat, solid separation with no gradients.

Best for:

- Spot color printing (Pantone inks)
- Designs with flat, distinct areas of color
- Text and logos
- When you need clean, sharp edges

How it works internally:

1. For each pixel, the algorithm calculates the distance to every palette color

2. The pixel is assigned to the **nearest** palette color
3. That channel gets a 255 alpha (fully opaque) at that position
4. All other channels get 0 alpha (transparent)

Sub-parameters:

Parameter	Range	Default	Description
Anti-Aliasing	On/Off	On	Applies a Gaussian blur + threshold to smooth jagged edges
AA Radius (Sigma)	0.1–5.0	1.0	How wide the smoothing area is. Higher = smoother but softer
AA Threshold (Cutoff)	1–254	127	The brightness threshold for the binary cutoff after blur

5.2 Raster (Soft / Gradient)

What it does: Assigns each pixel a **variable opacity** based on its color proximity to each palette color. This creates smooth gradients and soft transitions between colors.

Best for:

- Photographic or photorealistic designs
- Simulated process separations
- Designs with blends, shadows, or color transitions
- When you need smooth tonal reproduction

How it works internally:

1. For each pixel, the distance to every palette color is calculated
2. The opacity (alpha) of each channel at that pixel is computed using a **proximity × exclusivity** formula
3. Multiple channels can have non-zero alpha at the same pixel, creating overlapping ink zones
4. A gamma curve is applied to control the ink density falloff

Sub-parameters:

Parameter	Range	Default	Description
Adaptive Threshold	On/Off	On	Uses the maximum distance in each chunk as the reference, rather than a fixed global value. Results in better contrast.
Gamma	0.1–3.0	1.25	Global gamma for all channels. Controls the overall gradient falloff curve.

6. Understanding the Gradient System (Raster)

This is the **heart** of the raster engine and the key to mastering color separation for photographic prints. This section explains exactly how the system decides how much ink to place at each pixel.

6.1 How Color Distance Works

Every pixel in your image has an RGB color value. Each color in your palette also has an RGB value. The system measures "how different" a pixel is from each palette color using a **color distance** metric.

Pixel Color: (R=120, G=80, B=200) ← A purple pixel

Palette:

Color A (Red): #FF0000 → distance = 210
Color B (Blue): #0000FF → distance = 150
Color C (Purple): #7733CC → distance = 25 ← Closest!
Color D (White): #FFFFFF → distance = 220
Color E (Black): #000000 → distance = 180

The system calculates this distance for **every pixel** against **every palette color**, generating a distance matrix.

6.2 The Gradient Formula

For each pixel, the ink opacity of channel `i` is calculated as:

```
alpha = proximity × exclusivity × source_alpha
```

Where:

Proximity (How close is this pixel to this color?)

```
proximity = clamp(1.0 - (distance - ch_min) / ch_range, 0, 1)
```

- `distance` : How far this pixel is from palette color `i`
- `ch_min` : The "solidéz" value — distances below this are 100% solid
- `ch_range` : `ch_max - ch_min` — the gradient window width
- Result: **1.0** when the pixel is very close (solid ink), **0.0** when far away (no ink)

Exclusivity (Is this the dominant color here?)

```
exclusivity = clamp(1.0 - (distance - min_distance) / slope, 0, 1)
```

- `min_distance` : The distance to the **closest** palette color at this pixel
- If this IS the closest color: `distance - min_distance = 0` → exclusivity = 1.0
- If another color is closer: exclusivity drops, reducing ink
- This prevents colors from "bleeding" where they're not dominant

Gamma (Curve Adjustment)


```
final_alpha = alpha ^ gamma
```

- `gamma = 1.0` : Linear falloff (no change)
- `gamma > 1.0` : Reduces midtones, sharper transitions, less ink
- `gamma < 1.0` : Boosts midtones, softer transitions, more ink

Visual Representation

Ink Density

100% ██████████
 ██████████ .
 ██████████ . .
 ██████████ . . . ← `gamma < 1.0` (more ink in transitions)



6.3 Per-Channel Gradient Overrides

Each palette color can have its own **Solidez (Min)**, **Alcance (Max)**, and **Gamma** values. This lets you control the gradient behavior of each ink independently.

Solidez (Min) — "Solid Zone Width"

- **Low value (0–10):** Only pixels very close to this exact color get solid ink
- **High value (50–100):** A wider range of similar colors get solid ink
- **Use case:** Increase this for colors that need a strong, opaque core (like white underbase)

Alcance (Max) — "Gradient Reach"

- **Low value (5–30):** Ink cuts off quickly. Sharp transitions.
- **High value (100–200):** Ink gradually fades over a longer distance. Soft, wide gradients.
- **Use case:** Set high for colors that need to blend into other colors (like skin tones)

Gamma — "Curve Shape"

- **0.1–0.9:** Boosts midtones → more ink in transition zones, softer blends
- **1.0:** Linear (no adjustment)
- **1.1–3.0:** Suppresses midtones → less ink in transitions, crisper edges

6.4 Practical Scenario: Gradient Between Only 2 of 5 Colors

Problem: You have a design with 5 colors: Red, Blue, Purple, White, Black. You want a smooth gradient between Red and Blue (through Purple), but you want White and Black to remain **completely solid** with **no gradient**.

Solution: Use per-channel gradient overrides to restrict the gradient range.

Step-by-Step:

1. **Select Raster mode** in the Separation Engine section
2. **For Red (#FF0000):** Click the slider icon (⊞)
 - Solidez (Min): **10** — Small solid core
 - Alcance (Max): **120** — Wide gradient reach (allows blending with blue)
 - Gamma: **0.80** — Slightly boosted midtones for a smoother gradient
3. **For Blue (#0000FF):** Click the slider icon (⊞)
 - Solidez (Min): **10** — Small solid core
 - Alcance (Max): **120** — Wide gradient reach (allows blending with red)
 - Gamma: **0.80** — Match red's curve
4. **For Purple (#7733CC):** Leave at **Auto**

- The purple zone naturally lives in the gradient between red and blue. Auto handles this well.


5. **For White (#FFFFFF):** Click the slider icon (⊗)

- Solidez (Min): **80** — Very wide solid zone
- Alcance (Max): **5** — Almost no gradient → hard cutoff
- Gamma: **2.5** — Aggressively suppress any remaining transitions

6. **For Black (#000000):** Click the slider icon (⊗)

- Solidez (Min): **80** — Very wide solid zone
- Alcance (Max): **5** — Almost no gradient → hard cutoff
- Gamma: **2.5** — Aggressively suppress any remaining transitions

What Happens:



- Red and Blue have wide Alcance values, so their ink fades gradually into each other
- White and Black have very narrow Alcance values and high Gamma, creating sharp solid areas
- Purple, being equidistant from Red and Blue, naturally receives gradient ink from both

[!TIP] If you want to **completely remove** the gradient from a color, set *Solidez (Min)* = 100 and *Alcance (Max)* = 5 . This essentially makes it behave like Vector mode for that specific color, while keeping the rest in Raster mode.

7. Color Distance Methods

The color distance method determines how "similarity" between colors is calculated.

CIEDE2000 (Recommended)

- **Perceptually uniform:** A difference of 10 between two blues "looks" the same as a difference of 10 between two reds
- Uses the **CIELAB** color space with corrections for human vision
- Configurable via three weights:
 - **kL** (Lightness): Default 1.0. Increase to make the algorithm more sensitive to brightness differences
 - **kC** (Chroma): Default 1.0. Increase to make it more sensitive to saturation differences
 - **kH** (Hue): Default 1.0. Increase to make it more sensitive to hue shifts
- **Slower** but more accurate

Euclidean (RGB)

- Simple geometric distance in RGB space: $\sqrt{(R_1 - R_2)^2 + (G_1 - G_2)^2 + (B_1 - B_2)^2}$
- **Not** perceptually uniform (blues and greens are treated differently from reds)
- **Faster** processing

- Good for designs with very distinct, well-separated colors

[!NOTE] For most screen printing work, **CIEDE2000** is recommended because it matches how the human eye perceives color differences, resulting in more natural separations.

8. Pre-Processing (Denoise)

Applied **before** separation to reduce image noise. Uses a **Bilateral Filter** which smooths noise while preserving sharp edges.

Parameter	Range	Default	Description
Intensidad Color (SigmaColor)	0–100	10	How aggressively similar colors are blended together. Low (0–15): Minimal smoothing, preserves detail. High (50–100): Cartoon-like effect, large flat areas.
Espacio (SigmaSpace)	0–20	5	How far (in pixels) the filter reaches. Low (0–5): Only immediately adjacent pixels. High (10–20): Blends over larger areas.

When to Use:

- **Photographed artwork:** Set to 15/7 to remove camera noise
- **Clean vector art:** Set to 0/0 (no denoising needed)
- **Textured designs:** Be careful — too much denoising destroys intentional texture

When NOT to Use:

- If your design already has clean, solid color areas
- If you need to preserve fine detail like fabric texture

9. Cleanup & Refinement

Applied **after** separation to clean up the generated channels.

Parameter	Range	Default	Description
Limpieza Inteligente	0–10	1	Removes small isolated spots and fills small holes using morphological operations (Opening + Closing). Scale-aware: adjusts kernel size based on image resolution. 0: No cleanup. 1–3: Light cleanup, removes specks. 5–7: Moderate, removes small artifacts. 8–10: Aggressive, may affect small details.
Suavizado Bordes	0–5	0	Applies a Gaussian blur to channel edges to smooth pixelation. 0: No smoothing. 1–2: Light anti-aliasing. 3–5: Noticeably soft edges (may cause ink bleed in printing).
Cobertura Mínima	0–5%	0.2%	Automatically discards any channel that covers less than this percentage of the total image area. 0.0%: Keep all channels. 0.2%: Remove channels with negligible content. 1–5%: Aggressively cull channels with little content.

[!WARNING] Setting **Limpieza Inteligente** above 5 can remove intentional small details like text serifs, thin lines, or stipple patterns. Always preview the result before exporting.

10. Substrate Knockout

Purpose: Removes ink from areas that match the color of the printing surface (e.g., a white t-shirt or colored paper).

When to use: When printing on colored substrates where you don't want to print ink that matches the substrate color.

Parameter	Range	Default	Description
Knockout Toggle	On/Off	Off	Enables/disables substrate knockout
Color Sustrato	Hex color	#FFFFFF	The color of the garment or paper. Click to pick from a color wheel or type a hex value.
Intensidad	10–120	50	How aggressively the knockout removes similar colors. Low (10–30): Only removes near-exact matches. High (80–120): Removes a wide range of colors similar to the substrate.

How It Works:

For each pixel, the system calculates the distance between the pixel color and the substrate color. If the pixel is close to the substrate color, the ink opacity is reduced proportionally.

```
substrate_mask = clamp(1.0 - (pixel_to_substrate_distance / threshold), 0, 1)
final_ink = ink_opacity × (1.0 - substrate_mask)
```

Example:

- Printing on a **white t-shirt** (#FFFFFF)
- All white areas of the design will have their ink removed
- With `Intensidad = 50` , light grays (e.g., #E0E0E0) will also be partially knocked out

11. Halftone (Bitmap)

Converts continuous-tone channels into **print-ready dot patterns**. This is essential for screen printing because screens can only pass ink or block it — there are no "half" amounts.

AM (Amplitude Modulation) — Dot Pattern

Traditional halftone with **regularly spaced dots** that vary in **size**.

Parameter	Range	Default	Description
LPI (Lines/Inch)	15–150	45	The dot frequency. 15–25 LPI: Very coarse, chunky dots (poster look). 35–55 LPI: Standard for textile screen printing. 65–85 LPI: Fine detail (requires high mesh count screens, 230+ mesh). 90–150 LPI: Photo-quality (requires very fine screens and precise registration).

Ángulo (Degrees)	0–90°	22.5°	The angle of the dot pattern. Using different angles per channel helps avoid moiré (interference patterns). Common angles: 0°, 22.5°, 45°, 67.5°.
------------------	-------	-------	--

FM (Frequency Modulation) — Stochastic Dithering

Uses **randomly placed same-size dots** (Floyd-Steinberg error diffusion).

- No LPI or angle settings needed
- **Pros:** No moiré patterns, excellent for photographic detail
- **Cons:** Can look "noisy" at low resolutions, harder to print consistently

[!TIP] **For beginners:** Start with AM at 45 LPI, 22.5° angle. This is the most forgiving setting for standard mesh screens (110–156 mesh).

12. AI Auto-Config

Uses **Google Gemini 2.5 Flash** to analyze your uploaded image and suggest optimal configuration.

How to Use:

1. Upload an image
2. Open **Configuración Avanzada**
3. Click 🧙 **AI Auto-Config**
4. A prompt modal appears — you can add specific instructions (e.g., "I'm printing on a dark garment") or leave empty
5. The AI analyzes the image and returns recommended settings

What the AI Can Suggest:

- Separation type (Vector vs Raster)
- Denoise intensity
- Cleanup strength
- Gamma value
- Halftone LPI and angle
- Substrate knockout settings
- Its reasoning (displayed after analysis)

[!NOTE] The AI uses **RAG (Retrieval-Augmented Generation)** — it references previously saved successful configurations from the `ai_memory` table. The more you train it, the better it gets.

13. Train IA (Machine Learning)

After completing a successful separation that produces good results, you can save the configuration to train the AI.

How to Use:

1. Complete a separation that you're satisfied with
2. Click 🧠 **Train IA** (appears below "Apply Bitmaps")
3. The current configuration, palette, and image metadata are saved to Supabase

What Gets Saved:

- All `AdvancedConfig` parameters

- Separation type (vector/raster)
- Image metadata (width, height, number of colors, palette hex values)
- Timestamp

[!IMPORTANT] Only train the AI with **good** results. The AI uses these saved configurations as reference examples for future suggestions. Bad data leads to bad suggestions.

14. Export Options

Click **Export Results** to see available options:

Option	Description
Save Composite	Downloads a single PNG showing all channels composited together (print simulation)
Download Channels (ZIP)	Downloads a ZIP file containing individual PNG files for each separation channel. Each file is named {index}_{hex_color}.png
Download PSD	Downloads a Photoshop file with each channel as a separate layer
Generate PDF Report	Creates a PDF document with technical specifications and channel previews

15. Loadouts (Presets)

Save and load complete configuration presets for different scenarios.

How to Use:

- **Save:** Enter a name and click save. All current `AdvancedConfig` settings are stored
- **Load:** Select a previously saved loadout to restore all settings
- Requires login (Supabase auth) for cloud-synced loadouts

Suggested Presets:

Preset Name	Type	Denoise	Cleanup	LPI	Use Case
Clean Vector Art	Vector	0/0	2	—	Logos, text, flat designs
Photo Raster	Raster	15/7	1	45	Photographs, gradients
Fine Detail	Raster	5/3	0	65	Detailed illustrations
Poster Print	Vector	10/5	3	25	Large format, coarse screens

16. Layer Operations (Pro-Shop)

After separation, you can manipulate individual channels:

Operation	Description
Visibility Toggle	Show/hide individual channels in the composite preview

Edit Color	Change the assigned ink color of a channel
Merge Layers	Combine two or more channels into one
Chop	Re-separate a single channel into sub-channels
Delete	Remove a channel entirely
Reorder (Drag)	Drag and drop to change the layer stacking order
Undo/Redo	Full history support for layer operations

Layer View Modes:

- **Tinted:** Shows the channel in its ink color
- **Grayscale:** Shows the ink density as black-to-white
- **Film Positive:** Black ink on white background (what the screen film looks like)

17. Keyboard Shortcuts & Tips

Shortcut	Action
Ctrl+Z	Undo (layer operations)
Ctrl+Shift+Z	Redo
F5	Reload page (after config changes)

Pro Tips:

- **Always preview before export.** Toggle layer visibility to inspect individual channels.
- **Use denoise sparingly.** Over-denoising creates a "posterized" look that separates poorly.
- **Match your LPI to your mesh count.** A good rule: $LPI \leq \text{mesh count} / 4$.
- **Substrate knockout is your friend** when printing on colored garments — it removes unnecessary ink deposits.

18. Parameter Reference Table

Parameter	Location	Type	Range	Default	Mode
sampleSize	Internal	Integer	1,000–100,000	25,000	Both
inkOpacity	Visual Opacity	Float	0–1	0.90	Both
kL	Internal	Float	0.1–2.0	1.0	Both
kC	Internal	Float	0.1–2.0	1.0	Both
kH	Internal	Float	0.1–2.0	1.0	Both
separationMethod	Engine	Enum	ciede2000 / euclidean	ciede2000	Both
separationType	Engine	Enum	vector / raster	vector	Both

outputDpi	Output Size	Integer	72–600	300	Both
outputSizeInches	Output Size	Float	1–30	3	Both
outputMeasurement	Output Size	Enum	width / height	width	Both
denoiseStrength	Pre-Process	Integer	0–100	10	Both
denoiseSpatial	Pre-Process	Integer	0–20	5	Both
useVectorAntiAliasing	Engine	Boolean	—	true	Vector
vectorAASigma	Engine	Float	0.1–5.0	1.0	Vector
vectorAAThreshold	Engine	Integer	1–254	127	Vector
useRasterAdaptive	Engine	Boolean	—	true	Raster
useSubstrateKnockout	Substrate	Boolean	—	false	Both
substrateColorHex	Substrate	Hex	—	#FFFFFF	Both
substrateThreshold	Substrate	Integer	10–120	50	Both
cleanupStrength	Cleanup	Integer	0–10	1	Both
smoothEdges	Cleanup	Integer	0–5	0	Both
minCoverage	Cleanup	Float	0–5%	0.2%	Both
halftoneType	Halftone	Enum	am / fm	am	Both
halftoneLpi	Halftone	Integer	15–150	45	AM only
halftoneAngle	Halftone	Float	0–90°	22.5°	AM only
gamma	Engine	Float	0.1–3.0	1.25	Raster
gradientMin	Per-Channel	Integer	0–100	Auto (0)	Raster
gradientMax	Per-Channel	Integer	5–200	Auto (60)	Raster
gamma (per-ch.)	Per-Channel	Float	0.1–3.0	Auto (1.25)	Raster

19. Glossary

Term	Definition
AM Halftone	Amplitude Modulation. Dots of varying size at fixed spacing.
FM Halftone	Frequency Modulation. Dots of fixed size at varying spacing (stochastic).
CIEDE2000	The most advanced color difference formula, designed to match human perception.
CIELAB	A color space that represents colors as Lightness (L), green-red axis (a), and blue-yellow axis (b).

Delta E (ΔE)	The numerical value of color difference. ΔE < 1 is imperceptible. ΔE > 10 is obviously different.
K-Means	A clustering algorithm that groups pixels into a specified number of color clusters.
LPI	Lines Per Inch. The density of halftone dots. Higher = finer.
Moiré	An undesired interference pattern caused by overlapping dot screens at conflicting angles.
Morphology	Image processing operations (opening, closing) that remove noise or fill gaps based on structural elements.
RAG	Retrieval-Augmented Generation. The AI retrieves past data to improve its suggestions.
RIP	Raster Image Processor. Software that converts artwork to halftone-ready film output.
Separation	The process of splitting an image into individual ink channels for screen printing.
Spot Color	A pre-mixed ink color applied as a single, solid layer.
Substrate	The material being printed on (t-shirt, paper, plastic).
Trapping	Slight overlap of adjacent colors to prevent gaps caused by registration errors.
Underbase	A layer of white ink printed first on dark garments so that top colors appear vibrant.